

۱- مسیر زیر را طی کنید:

Start / Control panel / Network and sharing center

۲- از سمت چپ صفحه (Task panel) گزینه settings Change adapter را انتخاب نمایید.



۳- کارت شبکه خودتان را انتخاب نماید و بر روی آن کلیك راست کنید



	Panel Network and Internet his network device Diagno	se this connection Rename
Local Area Conr Network cabl	ection	VPN —Pisconnected
Realtek RTL8	Status Diagnose	IAN Miniport (PPTP)
	Properties	1

۵- از پنجره باز شده و لیست موجود گزینه Properties را انتخاب نمایید. و سپس کلید Properties را انتخاب نمایید .

Networking		t rt (PPTP)	
Connect using:		IT (PP IP)	
Reatek RTL8139/810x Family Fast Bit	hemet NIC		
This connection uses the following items:	Configure		
Clent for Microsoft Networks	Networks	I	
Internet Protocol Version 4 (TCP/IPv Internet Protocol Version 4 (TCP/IPv + Unk-Layer Topology Discovery Mapp + Link-Layer Topology Discovery Resp	Per I/O Driver xonder		
Internet Protocol Version 4 (TCP/IPv Internet Protocol Version 4 (TCP/IPv Ink-Layer Topology Discovery Resp Ink-Layer Topology Discovery Resp Install	(4) per I/O Driver] *	
Internet Protocol Version 4 (TCP/IPv Internet Protocol Version 4 (TCP/IPv	Properties	J ¥	

۶- در پنجره باز شده IP خود را در باکس شماره یك و در بخش شماره Sub net Mask ۲ رو برو (۲۵۵٬۲۵۵٬۰۰) را تنظیم نموده و در پایان کلید OK را تنظیم نمایید.

neral 'ou can get IP settings assigned au his capability. Otherwise, you nee or the appropriate IP settings.					
Obtain an IP address automat	ically				
O Use the following IP address:			-		
IP address:					
Subnet mask:					
Default gateway:					
Obtain DNS server address au	itomatically				
Use the following DNS server	addresses:				
Preferred DNS server:					
Alternate DNS server:					
Validate settings upon exit		Adva	anced		

This document was created with Win2PDF available at http://www.daneprairie.com. The unregistered version of Win2PDF is for evaluation or non-commercial use only.